

# Deployit Command Plugin Manual

Version 3.7.3

## Table of Contents

Table of Contents	2
Preface	3
Overview	3
Features	3
Plugin Concepts	3
Command	3
Undo Command	3
Command Order	3
Requirements	3
Usage in Deployment Packages	3
Using the deployables and deployed	4
Deployable vs. Container Table	4
Deployed Actions Table	4
Sample Usage Senario - Provision a Tomcat server	4
CI Reference	5
Configuration Item Overview	5
Deployable Configuration Items	5
Deployed Configuration Items	5
Topology Configuration Items	5
Virtual Topology Configuration Items	5
Configuration Item Details	5
cmd.Command	5
cmd.DeployedCommand	6
overthere.CifsHost	6
overthere.Host	7
overthere.Jumpstation	8
overthere.LocalHost	8
overthere.SshHost	9
overthere.SshJumpstation	10

## Preface

This document describes the functionality provided by the Command Plugin.

Refer to the *Deployit Reference Manual* for background information on Deployit and deployment concepts.

## Overview

As a system administrator, the need occasionally arises to execute adhoc scripts or OS commands on remote systems. The process usually entails having to manually login to each system, copy any required resources to said system and finally executing scripts/commands to process the resources or configure the remote system. The process is acceptable for a single system, but tends not to scale when performing the tasks on entire server farms. The manual intensive process becomes tedious and error prone. The Command Plugin helps with these tedious processes and significantly reduces the chances of errors.

A system administrator could also use the Command Plugin to reuse existing deployment scripts with Deployit, before choosing to move the deployment logic to a more reusable, easily maintainable plugin form.

## Features

- Execute an OS (Unix, Windows) command on a host
- Execute a script on a host
- Associate undo commands
- Copy associated command resources to a host

## Plugin Concepts

### Command

A Command encapsulates an OS specific command, as one would enter at the command prompt of a native OS command shell. The OS command is captured in the Command's `commandLine` property; e.g. 'echo hello >> /tmp/hello.txt'. The Command also has the capability of uploading any dependent files to the target system and make those available to the `commandLine` with the use of a placeholder; e.g. 'cat \${uploadedHello.txt} >> /tmp/hello.txt'.

### Undo Command

An undo Command has the same characteristics as a Command, except that it reverses the effect of the original Command it is associated with. An undo Command usually runs when the associated Command is undeployed or upgraded.

### Command Order

The order in which the Command is run in relation to other commands. The order allows for the chaining of commands to create a logical sequence of events. For example, an install tomcat command would execute before an install web application command, while a start tomcat command would be the last in the sequence.

## Requirements

This plugin requires:

- **Deployit:** version 3.5+

## Usage in Deployment Packages

Please refer to *Packaging Manual* for more details about the DAR packaging format.

Sample DAR MANIFEST.MF entries defining a package that can (un)provision a tomcat server using an install and uninstall script

```
Manifest-Version: 1.0
Deployit-Package-Format-Version: 1.3
CI-Application: CommandPluginSample
CI-Version: 1.0

Name: install-tc-command
CI-type: cmd.Command
CI-order: 50
CI-commandLine: /bin/sh ${install-tc.sh} ${tomcat.zip}
```

```

CI-undoCommand: uninstall-tc-command
CI-dependencies-EntryValue-1: install-tc.sh
CI-dependencies-EntryValue-2: tomcat.zip
CI-name: install-tc-command

Name: uninstall-tc-command
CI-type: cmd.Command
CI-order: 45
CI-commandLine: /bin/sh ${uninstall-tc.sh}
CI-dependencies-EntryValue-1: uninstall-tc.sh
CI-name: uninstall-tc-command

Name: tomcat-6.0.32.zip
CI-name: tomcat.zip
CI-type: file.File

Name: install-tc.sh
CI-type: file.File
CI-name: install-tc.sh

Name: uninstall-tc.sh
CI-type: file.File
CI-name: uninstall-tc.sh

```

## Using the deployables and deployed

### Deployable vs. Container Table

The following table describes which deployable / container combinations are possible. Note that the CIs can only be targeted to containers derived from [Host](#).

Deployables	Containers	Generated Deployed
cmd.Command	overthere.Host	cmd.DeployedCommand

### Deployed Actions Table

The following table describes the effect a deployed has on its container.

Deployed	Create	Destroy	Modify
cmd.DeployedCommand	<ul style="list-style-type: none"> <li>Upload command resources to host</li> <li>Resolve command line placeholder references with absolute paths to the uploaded resource files on host</li> <li>Execute command line on host</li> </ul>	<ul style="list-style-type: none"> <li>Run the undo command associated with the deployed command, if exists. Actions are same as described for <i>Create</i></li> </ul>	<ul style="list-style-type: none"> <li>Run the undo command associated with the deployed command, if exists. Actions are same as described for <i>Create</i></li> <li>Run the modified command. Actions are same as described for <i>Create</i></li> </ul>

### Sample Usage Senario - Provision a Tomcat server

For illustration purposes, we take a simplistic view of installing Tomcat. In reality however, your installation of Tomcat would take on a far more comprehensive form.

Tomcat is distributed as a zip. For this example, we create an installation script to unzip the distribution on the host. The uninstall script simply shuts down a running Tomcat and deletes the installation directory.

#### Create the installation script (install-tc.sh)

```

#!/bin/sh
set -e
if [ -e "/apache-tomcat-6.0.32" ]
then
    echo "/apache-tomcat-6.0.32 already exists. remove to continue."
    exit 1
fi
unzip $1 -d /
chmod +x /apache-tomcat-6.0.32/bin/*.sh

```

#### Create the uninstall script (uninstall-tc.sh)

```

#!/bin/sh
set -e
/apache-tomcat-6.0.32/bin/shutdown.sh
rm -rf /apache-tomcat-6.0.32

```

**MANIFEST snippet defining the command to trigger the execution of the install script for the initial deployment**

The following command will be executed at order 50 in the generated step list. '/bin/sh' is used on the host to execute the install script which takes a single parameter, the absolute path to the tomcat.zip on the host. When the command is undeployed, uninstall-tc-command will be executed.

```
Name: install-tc-command
CI-type: cmd.Command
CI-order: 50
CI-commandLine: /bin/sh ${install-tc.sh} ${tomcat.zip}
CI-undoCommand: uninstall-tc-command
CI-dependencies-EntryValue-1: install-tc.sh
CI-dependencies-EntryValue-2: tomcat.zip
CI-name: install-tc-command
```

#### MANIFEST snippet defining the undo command to trigger the execution of the uninstall script for the undeploy

The undo command will be executed at order 45 in the generated step list. Note that it has a lower order than the install-tc-command. This ensures that the undo command will always run before the install-tc-command during an upgrade.

```
Name: uninstall-tc-command
CI-type: cmd.Command
CI-order: 45
CI-commandLine: /bin/sh ${uninstall-tc.sh}
CI-dependencies-EntryValue-1: uninstall-tc.sh
CI-name: uninstall-tc-command
```

See the Usage in Deployment Packages section for the complete MANIFEST.MF

## CI Reference

### Configuration Item Overview

#### Deployable Configuration Items

CI	Description
<a href="#">cmd.Command</a>	Command specification that is executed on a host

#### Deployed Configuration Items

CI	Description
<a href="#">cmd.DeployedCommand</a>	Command deployed to a Host

#### Topology Configuration Items

CI	Description
<a href="#">overthere.CifsHost</a>	A machine that can be connected to using either WinRM or Telnet and can perform file manipulation via the CIFS protocol
<a href="#">overthere.LocalHost</a>	The machine on which the Deployit Server is running on
<a href="#">overthere.SshHost</a>	A machine that can be connected to using ssh
<a href="#">overthere.SshJumpstation</a>	A machine that can be used to create a tunneled connection to the destination host

#### Virtual Topology Configuration Items

CI	Description
<a href="#">overthere.Host</a>	A machine that runs middleware, on which scripts can be executed, etc
<a href="#">overthere.Jumpstation</a>	Base class for jumpstations

### Configuration Item Details

#### cmd.Command

**Hierarchy** udm.BaseDeployable >> udm.BaseConfigurationItem

**Interfaces** udm.Tagable, udm.Deployable, udm.ConfigurationItem

Command specification that is executed on a host


Public Properties	
<b>order</b>	: <b>INTEGER</b> = 50
Order of the command	
<b>commandLine</b>	: <b>STRING</b>
Command line to execute on host. Dependent artifacts can be referred to using \${artifact name}.	
<b>dependencies</b>	: <b>SET_OF_CI</b> <file.File>
Artifacts that the command depends on	
<b>runUndoCommandOnUpgrade</b>	: <b>BOOLEAN</b> = true
Indicates whether the undoCommand should be run on an upgrade	
<b>tags</b>	: <b>SET_OF_STRING</b>
The tags to map deployables to containers.	
<b>undoCommand</b>	: <b>CI</b> <cmd.Command>
Command to execute when undeploying command	

## cmd.DeployedCommand

**Hierarchy** udm.BaseDeployed >> udm.BaseConfigurationItem

**Interfaces** udm.Deployed, udm.ConfigurationItem

Command deployed to a Host

Public Properties	
 <b>container</b>	: <b>CI</b> <udm.Container>
The container on which this deployed runs.	
<b>order</b>	: <b>INTEGER</b> = 50
Order of the command	
<b>commandLine</b>	: <b>STRING</b>
Command line to execute on host. Dependent artifacts can be referred to using \${artifact name}.	
<b>dependencies</b>	: <b>SET_OF_CI</b> <file.File>
Artifacts that the command depends on	
<b>deployable</b>	: <b>CI</b> <udm.Deployable>
The deployable that this deployed is derived from.	
<b>rerunCommand</b>	: <b>BOOLEAN</b>
Forces the command to be rerun.	
<b>runUndoCommandOnUpgrade</b>	: <b>BOOLEAN</b>
Indicates whether the undoCommand should be run on an upgrade	
<b>undoCommand</b>	: <b>CI</b> <cmd.Command>
Command to execute when undeploying command	

## overthere.CifsHost

**Hierarchy** [overthere.Host](#) >> udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** udm.Taggable, udm.ConfigurationItem, udm.Container, [overthere.HostContainer](#)

A machine that can be connected to using either WinRM or Telnet and can perform file manipulation via the CIFS protocol.

Public Properties	
<b>address</b>	: <b>STRING</b>
Address of the host	
<b>connectionType</b>	: <b>ENUM</b> [TELNET, WINRM_HTTP, WINRM_HTTPS] = TELNET
Connection Type	
<b>os</b>	: <b>ENUM</b> [WINDOWS, UNIX]
Operating system	
<b>password</b>	: <b>STRING</b>
Password to use for authentication	
<b>username</b>	: <b>STRING</b>
Username to connect with	
<b>cifsPort</b>	: <b>INTEGER</b> = 445
Port on which the CIFS server runs	

**deploymentGroup** : INTEGER

The deployment group of this container.

**jumpstation** : [CI<overthere.Jumpstation>](#)

If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.

**port** : INTEGER

Port on which the Telnet or WinRM server runs

**tags** : SET\_OF\_STRING

The tags to map deployables to containers.

**temporaryDirectoryPath** : STRING

Directory into which temporary files are stored. Will be cleaned up when the connection is closed.

**Hidden Properties**

**connectionTimeoutMillis** : INTEGER = 1200000

Connection Timeout Millis

**protocol** : STRING = cifs

Protocol

**tmpFileCreationRetries** : INTEGER = 1000

Tmp File Creation Retries

**winrmContext** : STRING = /wsman

Winrm Context

**winrmEnvelopSize** : INTEGER = 153600

Winrm Envelop Size

**winrmLocale** : STRING = en-US

Winrm Locale

**winrmTimeout** : STRING = PT60.000S

Winrm Timeout

**tmpDeleteOnDisconnect** : BOOLEAN = true

Whether to delete the temporary connection directory when the connection is closed

**Control Tasks****checkConnection**

Check connection

**overthere.Host**

**Hierarchy** udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** udm.Taggable, udm.ConfigurationItem, udm.Container,  
[overthere.HostContainer](#)

A machine that runs middleware, on which scripts can be executed, etc.

**Public Properties**

**os** : ENUM [WINDOWS, UNIX]

Operating system

**deploymentGroup** : INTEGER

The deployment group of this container.

**jumpstation** : [CI<overthere.Jumpstation>](#)

If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.

**tags** : SET\_OF\_STRING

The tags to map deployables to containers.

**temporaryDirectoryPath** : STRING

Directory into which temporary files are stored. Will be cleaned up when the connection is closed.

**Hidden Properties**

**connectionTimeoutMillis** : INTEGER = 1200000

Connection Timeout Millis

**protocol** : STRING

Protocol to use when connecting to this host

**tmpFileCreationRetries** : INTEGER = 1000

Tmp File Creation Retries

**tmpDeleteOnDisconnect** : **BOOLEAN** = true

Whether to delete the temporary connection directory when the connection is closed

#### Control Tasks

##### checkConnection

Check connection

## overthere.Jumpstation

**Hierarchy** [overthere.Host](#) >> udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** udm.Taggable, udm.ConfigurationItem, udm.Container,  
[overthere.HostContainer](#)

Base class for jumpstations

#### Public Properties

**deploymentGroup** : **INTEGER**

The deployment group of this container.

**jumpstation** : **CI**<[overthere.Jumpstation](#)>

If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.

**tags** : **SET\_OF\_STRING**

The tags to map deployables to containers.

#### Hidden Properties

**connectionTimeoutMillis** : **INTEGER** = 1200000

Connection Timeout Millis

**os** : **ENUM** [WINDOWS, UNIX] = UNIX

Os

**protocol** : **STRING**

Protocol to use when connecting to this host

**tmpFileCreationRetries** : **INTEGER** = 1000

Tmp File Creation Retries

**temporaryDirectoryPath** : **STRING**

Temporary Directory Path

**tmpDeleteOnDisconnect** : **BOOLEAN** = true

Whether to delete the temporary connection directory when the connection is closed

#### Control Tasks

##### checkConnection

Check connection

## overthere.LocalHost

**Hierarchy** [overthere.Host](#) >> udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** udm.Taggable, udm.ConfigurationItem, udm.Container,  
[overthere.HostContainer](#)

The machine on which the Deployit Server is running on.

#### Public Properties

**os** : **ENUM** [WINDOWS, UNIX]

Operating system

**deploymentGroup** : **INTEGER**

The deployment group of this container.

**jumpstation** : **CI**<[overthere.Jumpstation](#)>

If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.

**tags** : **SET\_OF\_STRING**

The tags to map deployables to containers.

**temporaryDirectoryPath** : **STRING**

Directory into which temporary files are stored. Will be cleaned up when the connection is closed.

#### Hidden Properties

**connectionTimeoutMillis** : **INTEGER** = 1200000



Connection Timeout Millis
<b>protocol</b> : <b>STRING</b> = local
Protocol
<b>tmpFileCreationRetries</b> : <b>INTEGER</b> = 1000
Tmp File Creation Retries
<b>tmpDeleteOnDisconnect</b> : <b>BOOLEAN</b> = true
Whether to delete the temporary connection directory when the connection is closed

### Control Tasks

#### checkConnection

Check connection

## overthere.SshHost

**Hierarchy** [overthere.Host](#) >> udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** [udm.Taggable](#), [udm.ConfigurationItem](#), [udm.Container](#),  
[overthere.HostContainer](#)

A machine that can be connected to using ssh.

### Public Properties

<b>address</b> : <b>STRING</b>
Address of the host
<b>connectionType</b> : <b>ENUM</b> [SFTP, SFTP_CYGWIN, SFTP_WINSSHD, SCP, SUDO, INTERACTIVE_SUDO, TUNNEL] = SFTP
Type of SSH connection to create
<b>os</b> : <b>ENUM</b> [WINDOWS, UNIX]
Operating system
<b>port</b> : <b>INTEGER</b> = 22
Port on which the SSH server runs
<b>username</b> : <b>STRING</b>
Username to connect with
<b>deploymentGroup</b> : <b>INTEGER</b>
The deployment group of this container.
<b>jumpstation</b> : <b>CI</b> < <a href="#">overthere.Jumpstation</a> >
If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.
<b>passphrase</b> : <b>STRING</b>
Optional passphrase for the private key in the private key file
<b>password</b> : <b>STRING</b>
Password to use for authentication
<b>privateKeyFile</b> : <b>STRING</b>
Private key file to use for authentication
<b>sudoUsername</b> : <b>STRING</b>
Username to sudo to when accessing files or executing commands
<b>tags</b> : <b>SET_OF_STRING</b>
The tags to map deployables to containers.
<b>temporaryDirectoryPath</b> : <b>STRING</b>
Directory into which temporary files are stored. Will be cleaned up when the connection is closed.

### Hidden Properties

<b>connectionTimeoutMillis</b> : <b>INTEGER</b> = 1200000
Connection Timeout Millis
<b>interactiveKeyboardAuthRegex</b> : <b>STRING</b> = .*Password:[ ]?
Regular expression to look for in keyboard-interactive authentication before sending the password
<b>protocol</b> : <b>STRING</b> = ssh
Protocol
<b>sudoCommandPrefix</b> : <b>STRING</b> = sudo -u {0}
Sudo command to prefix to the original command. The placeholder {0} is replaced with the sudoUsername
<b>sudoPasswordPromptRegex</b> : <b>STRING</b> = .*[Pp]assword.*:
Regular expression to look for in interactive sudo before sending the password

**tmpFileCreationRetries** : INTEGER = 1000

Tmp File Creation Retries

**allocateDefaultPty** : BOOLEAN = false

If true, a default pty is allocated when executing a command. All sudo implementations require it for interactive sudo, some even require it for normal sudo. Some SSH server implementations (notably the one on AIX 5.3) crash when it is allocated.

**sudoOverrideUmask** : BOOLEAN = false

If true, permissions are explicitly changed with chmod -R go+rX after uploading a file or directory with scp.

**sudoQuoteCommand** : BOOLEAN = false

If true, the original command is quoted when it is prefixed with sudoCommandPrefix

**tmpDeleteOnDisconnect** : BOOLEAN = true

Whether to delete the temporary connection directory when the connection is closed

### Control Tasks

#### checkConnection

Check connection

## overthere.SshJumpstation

**Hierarchy** [overthere.Jumpstation](#) >> [overthere.Host](#) >> udm.BaseContainer >> udm.BaseConfigurationItem

**Interfaces** udm.Tagable, udm.ConfigurationItem, udm.Container, [overthere.HostContainer](#)

A machine that can be used to create a tunneled connection to the destination host.

### Public Properties

**address** : STRING

Address of the host

**port** : INTEGER = 22

Port on which the SSH server runs

**username** : STRING

Username to connect with

**deploymentGroup** : INTEGER

The deployment group of this container.

**jumpstation** : CI<[overthere.Jumpstation](#)>

If this host is not directly reachable, specify a jumpstation here which can be used to reach this host.

**passphrase** : STRING

Optional passphrase for the private key in the private key file

**password** : STRING

Password to use for authentication

**privateKeyFile** : STRING

Private key file to use for authentication

**tags** : SET\_OF\_STRING

The tags to map deployables to containers.

### Hidden Properties

**connectionTimeoutMillis** : INTEGER = 1200000

Connection Timeout Millis

**connectionType** : ENUM[SFTP, SFTP\_CYGWIN, SFTP\_WINSSHD, SCP, SUDO, INTERACTIVE\_SUDO, TUNNEL] = TUNNEL

Connection Type

**interactiveKeyboardAuthRegex** : STRING = .\*Password:[ ]?

Regular expression to look for in keyboard-interactive authentication before sending the password

**os** : ENUM[WINDOWS, UNIX] = UNIX

Os

**protocol** : STRING = ssh

Protocol to use when connecting to this host

**tmpFileCreationRetries** : INTEGER = 1000

Tmp File Creation Retries

**temporaryDirectoryPath** : STRING

Temporary Directory Path

**tmpDeleteOnDisconnect** : **BOOLEAN** = true

Whether to delete the temporary connection directory when the connection is closed

#### Control Tasks

##### **checkConnection**

Check connection